



LIGO Laboratory / LIGO Scientific Collaboration

LIGO-T1100472-v13

LIGO

February 12, 2014

ADC and DAC Channel Usage for ISC

Rich Abbott, Peter Fritschel, Daniel Sigg

Distribution of this document:
LIGO Scientific Collaboration

This is an internal working note
of the LIGO Laboratory.

California Institute of Technology
LIGO Project – MS 18-34
1200 E. California Blvd.
Pasadena, CA 91125
Phone (626) 395-2129
Fax (626) 304-9834
E-mail: info@ligo.caltech.edu

Massachusetts Institute of Technology
LIGO Project – NW22-295
185 Albany St
Cambridge, MA 02139
Phone (617) 253-4824
Fax (617) 253-7014
E-mail: info@ligo.mit.edu

LIGO Hanford Observatory
P.O. Box 159
Richland WA 99352
Phone 509-372-8106
Fax 509-372-8137

LIGO Livingston Observatory
P.O. Box 940
Livingston, LA 70754
Phone 225-686-3100
Fax 225-686-7189

<http://www.ligo.caltech.edu/>

1 Purpose

This document lists the specific ADC and DAC channels used within the ISC I/O expansion chassis. In the following tables, the entries given in the ‘Signal’ column are *not* meant to be the exact DAQ channel name for that signal (though they may be); rather the entries are intended as descriptors to identify the actual hardware channel that is connected to a given ADC/DAC channel.

The reference document for the actual DAQ channel names is [T1000264](#), *List of ISC Photodetectors in Advanced LIGO*.

2 ASC-IO I/O Chassis

Card	AA/AI conn.	ADC/DAC Chns.	Signal			
ADC 0	DB9_1	1	IMC-WFS_A_RF	Seg 1	Q-phase	
		2			I-phase	
		3		Seg 2	Q-phase	
		4			I-phase	
	DB9_2	5		IMC-WFS_B_RF	Seg 3	Q-phase
		6				I-phase
		7			Seg 4	Q-phase
		8				I-phase
	DB9_3	9	IMC-WFS_B_RF		Seg 1	Q-phase
		10				I-phase
		11			Seg 2	Q-phase
		12				I-phase
	DB9_4	13		IMC-WFS_B_RF	Seg 3	Q-phase
		14				I-phase
		15			Seg 4	Q-phase
		16				I-phase
	DB9_5	17-20	IMC-WFS_A_DC		Segs 1-4	DC Outputs of WFS
	DB9_6	21-24	IMC-WFS_B_DC		Segs 1-4	
	DB9_7	25	Unused			
		26	Unused			
		27	Unused			
		28	Unused			
	DB9_8	29-30	Unused			
		31	Duotone (DAC)			
		32	Duotone			

Card	AA/AI conn.	ADC/DAC Chs.	Signal		
ADC 1	DB9_1	1-4	IO QPD: SM2 Transmission		
	DB9_2	5-8	IO QPD: MC2 Transmission		
	DB9_3	9	PD 1: post-EOM		4 ch Generic PD interface: PSL/IO table
		10	PD 2: post-power control		
		11	PD 3: unused		
		12	PD 4: unused		
	DB9_4	13	PD 1: SM1 Transmission		4 ch Generic PD interface: IOT1
		14	PD 2: IMC_PDH DC out		
		15-16	PD 3,4: unused		
	DB9_5	17	PD 1: SM2 Fwd Trans		4 ch Generic PD interface: IOT2
		18	PD 2: SM2 Bwd Trans		
		19-20	PD 3,4: unused		
	DB9_6	21-24	Unused		
	DB9_7	25-28	Unused		
DB9_8	29-32	Unused			

Card	AA/AI conn.	ADC/DAC chan.	Signal			
ADC 2	DB9_1	1	ASC-REFL(AIR)_A_RF9	Seg 1	Q-phase	
		2			I-phase	
		3		Seg 2	Q-phase	
		4			I-phase	
	DB9_2	5		ASC-REFL(AIR)_A_RF45	Seg 3	Q-phase
		6				I-phase
		7			Seg 4	Q-phase
		8				I-phase
	DB9_3	9	ASC-REFL(AIR)_B_RF9		Seg 1	Q-phase
		10				I-phase
		11			Seg 2	Q-phase
		12				I-phase
	DB9_4	13		ASC-REFL(AIR)_B_RF45	Seg 3	Q-phase
		14				I-phase
		15			Seg 4	Q-phase
		16				I-phase
	DB9_5	17	ASC-REFL(AIR)_A_RF9		Seg 1	Q-phase
		18				I-phase
		19			Seg 2	Q-phase
		20				I-phase
	DB9_6	21		ASC-REFL(AIR)_B_RF9	Seg 3	Q-phase
		22				I-phase
		23			Seg 4	Q-phase
		24				I-phase
	DB9_7	25	ASC-REFL(AIR)_B_RF45		Seg 1	Q-phase
		26				I-phase
		27			Seg 2	Q-phase
		28				I-phase
	DB9_8	29		ASC-REFL(AIR)_A_RF9	Seg 3	Q-phase
		30				I-phase
		31			Seg 4	Q-phase
		32				I-phase

Card	AA/AI conn.	ADC/DAC chan.	Signal			
ADC 3	DB9_1	1	ASC-REFL_C_RF Spare Set of WFS Channels (1)	Seg 1	Q-phase	
		2			I-phase	
		3		Seg 2	Q-phase	
		4			I-phase	
	DB9_2	5		Seg 3	Q-phase	
		6			I-phase	
		7			Seg 4	Q-phase
		8				I-phase
	DB9_3	9	ASC-AS_D_RF Spare Set of WFS Channels (2)	Seg 1	Q-phase	
		10			I-phase	
		11		Seg 2	Q-phase	
		12			I-phase	
	DB9_4	13		Seg 3	Q-phase	
		14			I-phase	
		15			Seg 4	Q-phase
		16				I-phase
	DB9_5	17-20	ASC-REFL_A_DC	DC Outputs of WFS		
	DB9_6	21-24	ASC-REFL_B_DC			
	DB9_7	25	ALS-C_SHG_IR_LF	Aux. signals concentrator 3: REFL PD Amp 1-4		
		26	ALS-C_SHG_GR_LF			
		27	ALS-C_TRX_A_LF			
		28	ALS-C_TRY_A_LF			
	DB9_8	29-32	unused			

Card	AA/AI conn.	ADC/DAC chan.	Signal			
ADC 4	DB9_1	1	ASC-AS(AIR)_A_RF45	Seg 1	Q-phase	
		2			I-phase	
		3		Seg 2	Q-phase	
		4			I-phase	
	DB9_2	5		ASC-AS(AIR)_A_RF36	Seg 3	Q-phase
		6				I-phase
		7			Seg 4	Q-phase
		8				I-phase
	DB9_3	9	ASC-AS(AIR)_B_RF45		Seg 1	Q-phase
		10				I-phase
		11			Seg 2	Q-phase
		12				I-phase
	DB9_4	13		ASC-AS(AIR)_B_RF36	Seg 3	Q-phase
		14				I-phase
		15			Seg 4	Q-phase
		16				I-phase
	DB9_5	17	ASC-AS(AIR)_A_RF45		Seg 1	Q-phase
		18				I-phase
		19			Seg 2	Q-phase
		20				I-phase
	DB9_6	21		ASC-AS(AIR)_B_RF45	Seg 3	Q-phase
		22				I-phase
		23			Seg 4	Q-phase
		24				I-phase
	DB9_7	25	ASC-AS(AIR)_B_RF36		Seg 1	Q-phase
		26				I-phase
		27			Seg 2	Q-phase
		28				I-phase
	DB9_8	29		ASC-AS(AIR)_A_RF45	Seg 3	Q-phase
		30				I-phase
		31			Seg 4	Q-phase
		32				I-phase

Card	AA/AI conn.	ADC/DAC Chs.	Signal	
ADC 5	DB9_1	1-4	ASC-REFLAIR_A_DC	DC Outputs of WFS
	DB9_2	5-8	ASC-REFLAIR_B_DC	
	DB9_3	9-12	ASC-ASAIR_A_DC	
	DB9_4	13-16	ASC-ASAIR_B_DC	
	DB9_5	17-20	ASC-AS_A_DC	
	DB9_6	21-24	ASC-AS_B_DC	
	DB9_7	25-28	REFL TT1	Tip-Tilt Coil driver readbacks
	DB9_8	29-32	REFL TT2	

Card	AA/AI conn.	ADC/DAC Chs.	Signal	
ADC 6	DB9_1	1-4	ASC-POP_A (QPD)	
	DB9_2	5-8	ASC-POP_B (QPD)	
	DB9_3	9-12	ASC-AS_C (QPD)	
	DB9_4	13-16	ASC-OMC_A (QPD)	
	DB9_5	17-20	ASC-OMC_B (QPD)	
	DB9_6	21-24	ASC-OMCR_A (QPD)	
	DB9_7	25-28	ASC-OMCR_B (QPD)	
	DB9_8	29-32	Unused	

Card	AA/AI conn.	ADC/DAC Chs.	Signal	
ADC 7	DB9_1	1-4	AS TT1	Tip-Tilt BOSEM sensor signals
	DB9_2	5-8	AS TT2	
	DB9_3	9-12	AS TT3	
	DB9_4	13-16	REFL TT1	
	DB9_5	17-20	REFL TT2	
	DB9_6	21-24	AS TT1	Tip-Tilt Coil driver readbacks
	DB9_7	25-28	AS TT2	
	DB9_8	29-32	AS TT3	

Card	AA/AI conn.	ADC/DAC Chs.	Signal
DAC 0	DB9_1	1-4	AS TT1 Coil drives (UL, LL, UR, LR)
	DB9_2	5-8	AS TT2 Coil drives (UL, LL, UR, LR)
	DB9_3	9-12	AS TT3 Coil drives (UL, LL, UR, LR)
	DB9_4	13-15	Unused
		16	Duotone

Card	AA/AI conn.	ADC/DAC Chs.	Signal
DAC 1	DB9_1	1-4	REFL TT1 Coil drives (UL, LL, UR, LR)
	DB9_2	5-8	REFL TT2 Coil drives (UL, LL, UR, LR)
	DB9_3	9	IO Input beam tip-tilt PZT drive: pitch
		10	IO Input beam tip-tilt PZT drive: yaw
		11-12	Unused
	DB9_4	13-16	Unused

3 LSC I/O Chassis

Card	AA/AI conn.	ADC/DAC Chns.	Signal
ADC 0	DB9_1	1	PD 1: ALS-C_DIFF_A_LF
		2	PD 2: ALS-C_COMM_A_LF
		3	PD 3: LSC-REFLAIR_B_LF
		4	PD 4: LSC-POPAIR_B_LF
	DB9_2	5	LSC-POPAIR_A
		6	LSC-REFLAIR_A
		7	LSC-POP_A
		8	LSC-REFL_A
	DB9_3	9	PD1: LSC-ASAIR_A_LF
		10	PD2: LSC-ASAIR_B_LF
		11	PD3: Unused
		12	PD4: Unused
	DB9_4	13	OMC-DCPD_A
		14	OMC-DCPD_B
		15-16	Unused
	DB9_5	17	OMC PZT Monitor: Slow path
		18	OMC PZT Monitor: AC path
		19-20	Unused
	DB9_6	21	LSC-REFL_SERVO_ERR, CM Servo, I monitor
		22	LSC-REFL_SERVO_CTRL, CM Servo, Fast monitor
		23	LSC-REFL_SERVO_SLOW, CM Servo, Slow monitor
		24	Unused
	DB9_7	25	IMC-I, IMC Servo, I monitor
		26	IMC-F, IMC Servo, Fast monitor
		27	IMC-L, IMC Servo, Slow monitor
		28	Unused
	DB9_8	29	Unused
		30	Unused
		31	Duotone (DAC)
		32	Duotone

Card	AA/AI conn.	ADC/DAC Chns.	Signal		
ADC 1	DB9_1	1	LSC-POPAIR_B	RF18	Q-phase
		2			I-phase
		3		RF90	Q-phase
		4			I-phase
	DB9_2	5	LSC-REFLAIR_B	RF27	Q-phase
		6			I-phase
		7		RF135	Q-phase
		8			I-phase
	DB9_3	9	LSC-ASAIR_B	RF18	Q-phase
		10			I-phase
		11		RF90	Q-phase
		12			I-phase
	DB9_4	13	LSC-ASAIR_A	RF45	Q-phase
		14	I-phase		
		15	Unused	Q-phase	
		16		I-phase	
	DB9_5	17	LSC-POPAIR_A	RF9	Q-phase
		18			I-phase
		19		RF45	Q-phase
		20			I-phase
	DB9_6	21	LSC-REFLAIR_A	RF9	Q-phase
		22			I-phase
		23		RF45	Q-phase
		24			I-phase
	DB9_7	25	LSC-POP_A	RF9	Q-phase
		26			I-phase
		27		RF45	Q-phase
		28			I-phase
	DB9_8	29	LSC-REFL_A	RF9	Q-phase
		30			I-phase
		31		RF45	Q-phase
		32			I-phase

Card	AA/AI conn.	ADC/DAC Chns.	Signal	
ADC 2	DB9_1	1	IMC-REFL_A_DC, RF PD DC output (whitened)	
		2	ALS-C_DIFF_A_RF_ERR PFD signal for ALS Differential	
		3	PD3: Unused	
		4	PD4: Unused	
	DB9_2	5	ALS-C_REFL_DC_ERR CM: DC signal from REFL_A PD	CM Summing Module Readback
		6	LSC-REFL_A_RF9_ERR CM: Demodulator signal REFL	
		7	ALS-C_COMM_A_RF_ERR CM: PFD signal ALS Common	
		8	LSC-REFLAIR_A_RF9_ERR CM: Demodulator signal REFLAIR	
	DB9_3	9	LSC EXTRA_AI_1	
		10	LSC EXTRA_AI_2	
		11	ALS-REQSTATE_A (EtherCAT interface)	
		12	ALS-REQSTATE_B (EtherCAT interface)	
	DB9_4	13	ALS-C_COMM_PLL_ERR	
		14	ALS-C_COMM_PLL_CTRL	
		15	ALS-C_DIFF_PLL_ERR	
		16	ALS-C_DIFF_PLL_CTRL	
	DB9_5	17	Unused	
		18	Unused	
		19	Unused	
		20	Unused	
	DB9_6	21-24	Unused	
	DB9_7	25-28	Unused	
	DB9_8	29-32	Unused	

Card	AA/AI conn.	ADC/DAC Chs.	Signal
DAC 0	DB9_1	1	OMC PZT Dither
		2	OMC PZT Drive (feedback)
		3	Fast Shutter control
		4	Unused
	DB9_2	5	Unused
		6	Unused
		7	Unused
		8	Unused
	DB9_3	9	ALS-C_REFL_DC_BIAS CM Summing module control
		10	LSC EXTRA_AO_2
		11	ALS STATE_A (EtherCAT interface)
		12	ALS STATE_B (EtherCAT interface)
	DB9_4	13	Unused
		14	Unused
		15	Unused
		16	Duotone

4 End Stations

The first ADC card (ADC 0) is used by PEM and Photon Calibrator. The first ISC card is ADC 1.

Card	AA/AI conn.	ADC/DAC Chs.	Signal		
ADC 0	DB9_1	1-4	ASC-TRX(Y)_A		
	DB9_2	5-8	ASC-TRX(Y)_B		
	DB9_3	9-12	ALS-X(Y)_QPD_A		
	DB9_4	13-16	ALS-X(Y)_QPD_B		
	DB9_5	17 18 19 20	ALS-X(Y)_WFS_A	Seg 1	DC
				Seg 2	DC
				Seg 3	DC
				Seg 4	DC
	DB9_6	21 22 23 24	ALS-X(Y)_WFS_B	Seg 1	DC
				Seg 2	DC
				Seg 3	DC
				Seg 4	DC
	DB9_7	25	LSC-X(Y) EXTRA_AI_1		
		26	LSC-X(Y) EXTRA_AI_2		
		27	LSC-X(Y) EXTRA_AI_3		
		28	ALS-X(Y) REQSTATE_A (EtherCAT interface)		
	DB9_8	29	Unused		
		30	Unused		
		31	Duotone (DAC)		
		32	Duotone		

Card	AA/AI conn.	ADC/DAC Chs.	Signal	
ADC 1	DB9_1	1	ALS-X(Y)_FIBR_SERVO_ERR CM Servo: ALS phase-locking, I monitor	
		2	ALS-X(Y)_FIBR_SERVO_CTRL CM Servo: ALS phase-locking, Fast monitor	
		3	ALS-X(Y)_FIBR_SERVO_SLOW CM Servo: ALS phase-locking, Slow monitor	
		4	Unused	
	DB9_2	5	ALS-X(Y)_REFL_SERVO_ERR CM Servo: ALS PDH-locking, I monitor	
		6	ALS-X(Y)_REFL_SERVO_CTRL CM Servo: ALS PDH-locking, Fast monitor	
		7	ALS-X(Y)_FIBR_SERVO_SLOW CM Servo: ALS PDH-locking, Slow monitor	
		8	Unused	
	DB9_3	9	ALS-X(Y)_REFL_B_LF PD1: DC from REFL power mon.	4 ch. PD interface chassis: ALS Table
		10	LSC-TRX(Y)_A_LF PD2: Red transmitted beam	
		11	ALS-X(Y)_LASER_GR_LF PD3: Green power monitor	
		12	ALS-X(Y)_FIBR_A_LF PD4: DC from BBPD	
	DB9_4	13	ALS-X(Y)_LASER_IR_LF PD1: IR power monitor	4 ch. Aux. signals concentrator 5: Field rack
		14	ALS-X(Y)_FIBR_REJECTED_LF PD2: Rejected fiber power	
		15	ALS-X(Y)_FIBR_TRANS_LF PD3: Trans. fiber power	
		16	ALS-X(Y)_SPARE_B_LF PD4: unused	

Card	AA/AI conn.	ADC/DAC Chs.	Signal		
ADC1	DB9_5	17	ALS-X(Y)_WFS_A	Seg 1	Q-phase
		18			I-phase
		19		Seg 2	Q-phase
		20			I-phase
	DB9_6	21		Seg 3	Q-phase
		22			I-phase
		23		Seg 4	Q-phase
		24			I-phase
	DB9_7	25	ALS-X(Y)_WFS_B	Seg 1	Q-phase
		26			I-phase
		27		Seg 2	Q-phase
		28			I-phase
	DB9_8	29		Seg 3	Q-phase
		30			I-phase
		31		Seg 4	Q-phase
		32			I-phase

Card	AA/AI conn.	ADC/DAC Chs.	Signal
DAC 0	DB9_1	1	ALS-X(Y)_PZT1_PIT MCL PZT Tip-tilt 1: pitch
		2	ALS-X(Y)_PZT1_YAW MCL PZT Tip-tilt 1: yaw
		3	ALS-X(Y)_PZT2_PIT MCL PZT Tip-tilt 2: pitch
		4	ALS-X(Y)_PZT2_YAW MCL PZT Tip-tilt 2: yaw
	DB9_2	5	LSC-X(Y) EXTRA_AO_1
		6	LSC-X(Y) EXTRA_AO_2
		7	LSC-X(Y) EXTRA_AO_3
		8	ALS-X(Y) REQSTATE_A (EtherCAT interface)
	DB9_3	9-12	Unused
	DB9_4	13-15	Unused
		16	Duotone

5 Summary

Below is a summary of the number of I/O cards, unused channels, and available I/O slots for the ISC I/O Expansion Chassis. This assumes there are a total of 10 slots available in the I/O chassis for ADC and/or DAC cards. For the unused ADC channel column, the number in parentheses is the subset of these channels that are available Anti-Alias (AA) chassis on free DB9 connectors; the other channels are found on AA DB9 connectors which are only partially used.

I/O Chassis	# ADC cards	# DAC cards	Unused ADC chans	Unused DAC chans	Available I/O slots
Vertex: ASC-IO	8	2	38 (36)	9	0
Vertex: LSC	3	1	26 (16)	8	6
End X	2	1	28 (24)	7	5
End Y	2	1	28 (24)	7	5
Totals	15	5	120 (100)	31	16

At the end stations, the I/O Expansion Chassis is shared with PEM. PEM has one ADC card, of which 14 channels are used, and one DAC card. The DAC card provides 8 channels (18 bit) of general purpose test outputs. The ‘available slots’ number includes these PEM cards.